


[PFsense] Sécurisation PFsense


- [\[PFsense\] Changer le port du Pfsense](#)
- [\[PFsense\] Activer SSH](#)

[PFsense] Changer le port du PFSense

- Se connecter au WebGUI de PFSense




- Onglet system -> Advanced
 - Cocher la case HTTPS
 - TCP Port : 8443
 - Save

A screenshot of the webConfigurator settings page for HTTPS (SSL/TLS). The page is titled 'webConfigurator'. Under the 'Protocol' section, the 'HTTPS (SSL/TLS)' radio button is selected. The 'SSL/TLS Certificate' dropdown menu is set to 'webConfigurator default (62dba8c2447ab)'. Below this, there is a note: 'Certificates known to be incompatible with use for HTTPS are not included in this list.' The 'TCP port' field is set to '8443'. Below this field, there is a note: 'Enter a custom port number for the webConfigurator above to override the default (80 for HTTP, 443 for HTTPS). Cha...'.


webConfigurator	
Protocol	<input type="radio"/> HTTP <input checked="" type="radio"/> HTTPS (SSL/TLS)
SSL/TLS Certificate	webConfigurator default (62dba8c2447ab) <small>Certificates known to be incompatible with use for HTTPS are not included in this list.</small>
TCP port	8443 <small>Enter a custom port number for the webConfigurator above to override the default (80 for HTTP, 443 for HTTPS). Cha... -----</small>

[PFsense] Activer SSH

- Se connecter au WebGUI de PFSense



- Onglet system -> Advanced
 - Cocher la case, « Enable Secure Shell »

A screenshot of the 'Secure Shell' configuration page in PFSense. The page has a dark header with the title 'Secure Shell'. Below the header, there are several configuration sections:

- Secure Shell Server**: A checkbox labeled 'Enable Secure Shell' is checked.
- SSHd Key Only**: A dropdown menu is set to 'Password or Public Key'. Below it, there is a note: 'When set to *Public Key Only*, SSH access requires authorized keys and these access. If set to *Require Both Password and Public Key*, the SSH daemon req default *Password or Public Key* setting allows either a valid password or a va'.
- Allow Agent Forwarding**: A checkbox labeled 'Enables ssh-agent forwarding support.' is unchecked.
- SSH port**: A text input field contains the number '22'. Below it, there is a note: 'Note: Leave this blank for the default of 22.'

- Le port SSH est modifiable dans la section "SSH port"